

# UTLink Public Manifest



**Remotely  
Control your  
Prisma & Veo**



Image courtesy of Torngats



## Minimum System Requirements

Tablet or PC	Sonatest Instrument Supported
<ul style="list-style-type: none"><li>Operating System:<ul style="list-style-type: none"><li>Windows 32/64 bits 7, 8 &amp; 10</li></ul></li><li>System Memory:<ul style="list-style-type: none"><li>4GB ram recommended</li></ul></li><li>Free Disk Space:<ul style="list-style-type: none"><li>200MB of free space required</li></ul></li></ul>	

## Important information and recommendations

- Alpha-numeric values on the virtual instrument keypad are not supported, to edit a name the remote keyboard keys shall be used.
- Refresh rate is based on network performances, images may appear faster on the instrument than on the remote PC or tablet.

## 2017-02-10: UT-Link version 1.4.3

### New features

	<ul style="list-style-type: none"><li>New functionality to maximize the colour palettes when the connection is optimal (Max Color). Uncheck to optimize refresh network performances for slower connections.</li></ul>
	<ul style="list-style-type: none"><li>New folder button to have a direct access to the instrument internal memory drive and USB drives connected on instrument. <b>! ONLY for instrument software version 3.13 and higher !</b></li></ul>
	<ul style="list-style-type: none"><li>New button (F11) on corner of the keypad to expand interface window (full screen).</li></ul>

### Fixed

- General performance enhancements

### Known issues

- Application need to be restarted if PC goes in sleep mode.

## 2016-02-29: UT-Link version 1.3.3

### **New features**

- Support new product VEO+.
- Enhanced communication.

### **Fixed**

- FPS (frame per second rate information) is now correctly displayed.

## 2016-01-29: UT-Link version 1.2

### **New features**

- Support Windows 10 OS.

### **Fixed**

- none

## 2015-02-15: UT-Link version 1.1 (*first public release*)

### **New features**

- New product enjoy!